


# Home Assistant Server

By: Anastasiia Zatsepina (32265) & Ekaterina Zakharova (30909)



## 1. Introduction

In this project, our group explored the creation and implementation of a home automation system using a Raspberry Pi and the Home Assistant platform. The system integrates various smart devices and sensors to automate and enhance everyday home activities, focusing on practicality and ease of use.

*Key components* of the system include a Raspberry Pi, which serves as the central hub, and a range of smart devices such as Zigbee-based sensors, Tuya-controlled pet feeder, and lamp. These devices work together seamlessly to provide a connected and intelligent home environment. The project covers the setup and configuration of Home Assistant on the Raspberry Pi, offering a short guide to integrating and controlling various smart devices.

By using *Zigbee* technology, we combine motion and temperature sensors to monitor and automate home conditions. Additionally, *Node-RED* is utilized to create automation workflows, such as automating the pet feeder and responding to motion sensor triggers. Furthermore, the system includes the configuration of the E-mail Node in Node-RED to enable email notifications for specific events.

*InfluxDB* is employed for data storage and graphical representation, allowing for the visualization of sensor data and system performance over time. Overall, this project demonstrates the potential of home automation to simplify daily tasks, improve home security, and enhance the quality of life through the integration of smart technologies.

---

## 2. Materials

- Raspberry Pi 5 with installed HA
- Zigbee


- Motion and temperature/humidity sensors
- Tuya devices: pet feeder and lamp

## Raspberry Pi

The Raspberry Pi is a small, affordable, and versatile single-board computer that serves as the central hub for our home automation system (Figure 2.1). Its compact size, low power consumption, and robust performance make it an ideal choice for running Home Assistant and managing various smart devices. The Raspberry Pi supports a variety of operating systems and comes with multiple interfaces, including GPIO pins, USB ports, and HDMI, making it a highly adaptable tool for numerous applications[1].

## Home Assistant

Home Assistant is an open-source home automation platform that enables users to control and automate a wide range of smart devices[2]. It offers a user-friendly interface, extensive device compatibility, and powerful automation capabilities. Home Assistant can run on various hardware, including the Raspberry Pi, and supports integration with numerous smart home products and services, providing a centralized system for monitoring and controlling home environments.



| Figure 2.1 - Raspberry Pi 5 [Product page](#) | Figure 2.2 - Home assistant [Installation guideline by Taycan](#) |

---

**Home Assistant's** core components provide the foundation for integrating, controlling, and automating smart devices:

- Devices and area: Physical hardware with associated entities, providing a higher-level abstraction for managing related functions.
- Entities: function/sensor of a device. Helps to monitor physical properties of the area (Figure

2.3).

- Integrations: Modules connecting Home Assistant to various smart devices and services, expanding its capabilities.
- Automations: Custom rules and actions triggered by specific events, like turning on lights when motion is detected.
- States: The current condition or value of an entity (e.g., the temperature reading from a sensor)(Figure 2.4).

↑ Name	Entity ID	Integration
 _TZ1800_fcdjzz3s TY0202 Battery	sensor.tz1800_fcdjzz3s_ty0202_battery	Zigbee Home Automation

*Figure 2.3 - Zigbee device: area, manufacturer and model & entities*

Entity	State	Attributes <input checked="" type="checkbox"/>
 Filter entities  motion	 Filter states	 Filter attributes
 <a href="#">binary_sensor.tz1800_fcdjzz3s_ty0202_motion</a>	off	device_class: motion friendly_name: _TZ1800_fcdjzz3s TY0202 Motion
 _TZ1800_fcdjzz3s TY0202 Motion		

*Figure 2.4 - Zigbee device: state*

- Add-ons: Additional applications or services like Node-RED for advanced automation, InfluxDB for data storage, and Grafana for visualization.
- Services: Actions performed on entities or devices, like turning a light on or off.

## Zigbee

Zigbee is a wireless communication protocol designed for low-power, low-data-rate, and close-proximity applications (Figure 2.5). It is widely used in home automation, smart lighting, and other IoT (Internet of Things) applications[3]. Using Zigbee with a Raspberry Pi for Home Assistant involves setting up a Zigbee gateway (or hub) that connects to Raspberry Pi, allowing Home Assistant to communicate with Zigbee devices. The first step is setting up the necessary integration for zigbee.



*Figure 2.5 - Zigbee*

## 3. Set up

1. Home assistant
2. Integrate own Wifi AP/Router
3. Setup MQTT
4. Setup Node-RED
5. Setup INfluxDB
6. Setup local Tuya extension

(with Pet Feeder(Tuya), Tuya lamp, Zigbee Motion + Temperature sensors as components of the system)

### 1) Installation of Home Assistant on Raspberry Pi

- Installation guide can be found at [Home Assistant Installation](#) (guide was written using Home Assistant version 2024.5.x.)
- Credits go to Taycan.

### 2) Wifi AP integration

1. In HA settings, select “Automatic” on both IPv4 & IPv6
2. Connect to your Wifi Access point




Fig. 1

### 3) MQTT setup

1. Go to “Settings”→Add-ons→Add-on store→Find the “Mosquito broker” add-on and click it→Click

## "Install"

&lt;img alt="Screenshot of the Home Assistant 'Install' page showing the Mosquitto broker add-on. The sidebar on the left shows 'Overview', 'Map', 'Energy', 'Logbook', 'History', 'Media', and 'To-do lists'. The main content area shows the Mosquitto broker add-on with a 'Mosquitto broker' title, a 'Changelog' section, and a '6.4.1' version. It features a large 'MQTT' logo with a purple and white design. Below the logo is a 'INSTALL' button. The 'About' section describes the add-on as an MQTT broker for Home Assistant, mentioning support for Mosquitto 1.7.12, 1.7.11, 1.7.10, 1.7.9, 1.7.8, 1.7.7, 1.7.6, 1.7.5, 1.7.4, 1.7.3, 1.7.2, 1.7.1, 1.7.0, 1.6.9, 1.6.8, 1.6.7, 1.6.6, 1.6.5, 1.6.4, 1.6.3, 1.6.2, 1.6.1, 1.6.0, 1.5.9, 1.5.8, 1.5.7, 1.5.6, 1.5.5, 1.5.4, 1.5.3, 1.5.2, 1.5.1, 1.5.0, 1.4.9, 1.4.8, 1.4.7, 1.4.6, 1.4.5, 1.4.4, 1.4.3, 1.4.2, 1.4.1, 1.4.0, 1.3.9, 1.3.8, 1.3.7, 1.3.6, 1.3.5, 1.3.4, 1.3.3, 1.3.2, 1.3.1, 1.3.0, 1.2.9, 1.2.8, 1.2.7, 1.2.6, 1.2.5, 1.2.4, 1.2.3, 1.2.2, 1.2.1, 1.2.0, 1.1.9, 1.1.8, 1.1.7, 1.1.6, 1.1.5, 1.1.4, 1.1.3, 1.1.2, 1.1.1, 1.1.0, 1.0.9, 1.0.8, 1.0.7, 1.0.6, 1.0.5, 1.0.4, 1.0.3, 1.0.2, 1.0.1, 1.0.0, 0.10.9, 0.10.8, 0.10.7, 0.10.6, 0.10.5, 0.10.4, 0.10.3, 0.10.2, 0.10.1, 0.10.0, 0.9.9, 0.9.8, 0.9.7, 0.9.6, 0.9.5, 0.9.4, 0.9.3, 0.9.2, 0.9.1, 0.9.0, 0.8.9, 0.8.8, 0.8.7, 0.8.6, 0.8.5, 0.8.4, 0.8.3, 0.8.2, 0.8.1, 0.8.0, 0.7.9, 0.7.8, 0.7.7, 0.7.6, 0.7.5, 0.7.4, 0.7.3, 0.7.2, 0.7.1, 0.7.0, 0.6.9, 0.6.8, 0.6.7, 0.6.6, 0.6.5, 0.6.4, 0.6.3, 0.6.2, 0.6.1, 0.6.0, 0.5.9, 0.5.8, 0.5.7, 0.5.6, 0.5.5, 0.5.4, 0.5.3, 0.5.2, 0.5.1, 0.5.0, 0.4.9, 0.4.8, 0.4.7, 0.4.6, 0.4.5, 0.4.4, 0.4.3, 0.4.2, 0.4.1, 0.4.0, 0.3.9, 0.3.8, 0.3.7, 0.3.6, 0.3.5, 0.3.4, 0.3.3, 0.3.2, 0.3.1, 0.3.0, 0.2.9, 0.2.8, 0.2.7, 0.2.6, 0.2.5, 0.2.4, 0.2.3, 0.2.2, 0.2.1, 0.2.0, 0.1.9, 0.1.8, 0.1.7, 0.1.6, 0.1.5, 0.1.4, 0.1.3, 0.1.2, 0.1.1, 0.1.0, 0.0.9, 0.0.8, 0.0.7, 0.0.6, 0.0.5, 0.0.4, 0.0.3, 0.0.2, 0.0.1, 0.0.0, 0.0.0.1, 0.0.0.2, 0.0.0.3, 0.0.0.4, 0.0.0.5, 0.0.0.6, 0.0.0.7, 0.0.0.8, 0.0.0.9, 0.0.0.10, 0.0.0.11, 0.0.0.12, 0.0.0.13, 0.0.0.14, 0.0.0.15, 0.0.0.16, 0.0.0.17, 0.0.0.18, 0.0.0.19, 0.0.0.20, 0.0.0.21, 0.0.0.22, 0.0.0.23, 0.0.0.24, 0.0.0.25, 0.0.0.26, 0.0.0.27, 0.0.0.28, 0.0.0.29, 0.0.0.30, 0.0.0.31, 0.0.0.32, 0.0.0.33, 0.0.0.34, 0.0.0.35, 0.0.0.36, 0.0.0.37, 0.0.0.38, 0.0.0.39, 0.0.0.40, 0.0.0.41, 0.0.0.42, 0.0.0.43, 0.0.0.44, 0.0.0.45, 0.0.0.46, 0.0.0.47, 0.0.0.48, 0.0.0.49, 0.0.0.50, 0.0.0.51, 0.0.0.52, 0.0.0.53, 0.0.0.54, 0.0.0.55, 0.0.0.56, 0.0.0.57, 0.0.0.58, 0.0.0.59, 0.0.0.60, 0.0.0.61, 0.0.0.62, 0.0.0.63, 0.0.0.64, 0.0.0.65, 0.0.0.66, 0.0.0.67, 0.0.0.68, 0.0.0.69, 0.0.0.70, 0.0.0.71, 0.0.0.72, 0.0.0.73, 0.0.0.74, 0.0.0.75, 0.0.0.76, 0.0.0.77, 0.0.0.78, 0.0.0.79, 0.0.0.80, 0.0.0.81, 0.0.0.82, 0.0.0.83, 0.0.0.84, 0.0.0.85, 0.0.0.86, 0.0.0.87, 0.0.0.88, 0.0.0.89, 0.0.0.90, 0.0.0.91, 0.0.0.92, 0.0.0.93, 0.0.0.94, 0.0.0.95, 0.0.0.96, 0.0.0.97, 0.0.0.98, 0.0.0.99, 0.0.0.100, 0.0.0.101, 0.0.0.102, 0.0.0.103, 0.0.0.104, 0.0.0.105, 0.0.0.106, 0.0.0.107, 0.0.0.108, 0.0.0.109, 0.0.0.110, 0.0.0.111, 0.0.0.112, 0.0.0.113, 0.0.0.114, 0.0.0.115, 0.0.0.116, 0.0.0.117, 0.0.0.118, 0.0.0.119, 0.0.0.120, 0.0.0.121, 0.0.0.122, 0.0.0.123, 0.0.0.124, 0.0.0.125, 0.0.0.126, 0.0.0.127, 0.0.0.128, 0.0.0.129, 0.0.0.130, 0.0.0.131, 0.0.0.132, 0.0.0.133, 0.0.0.134, 0.0.0.135, 0.0.0.136, 0.0.0.137, 0.0.0.138, 0.0.0.139, 0.0.0.140, 0.0.0.141, 0.0.0.142, 0.0.0.143, 0.0.0.144, 0.0.0.145, 0.0.0.146, 0.0.0.147, 0.0.0.148, 0.0.0.149, 0.0.0.150, 0.0.0.151, 0.0.0.152, 0.0.0.153, 0.0.0.154, 0.0.0.155, 0.0.0.156, 0.0.0.157, 0.0.0.158, 0.0.0.159, 0.0.0.160, 0.0.0.161, 0.0.0.162, 0.0.0.163, 0.0.0.164, 0.0.0.165, 0.0.0.166, 0.0.0.167, 0.0.0.168, 0.0.0.169, 0.0.0.170, 0.0.0.171, 0.0.0.172, 0.0.0.173, 0.0.0.174, 0.0.0.175, 0.0.0.176, 0.0.0.177, 0.0.0.178, 0.0.0.179, 0.0.0.180, 0.0.0.181, 0.0.0.182, 0.0.0.183, 0.0.0.184, 0.0.0.185, 0.0.0.186, 0.0.0.187, 0.0.0.188, 0.0.0.189, 0.0.0.190, 0.0.0.191, 0.0.0.192, 0.0.0.193, 0.0.0.194, 0.0.0.195, 0.0.0.196, 0.0.0.197, 0.0.0.198, 0.0.0.199, 0.0.0.200, 0.0.0.201, 0.0.0.202, 0.0.0.203, 0.0.0.204, 0.0.0.205, 0.0.0.206, 0.0.0.207, 0.0.0.208, 0.0.0.209, 0.0.0.210, 0.0.0.211, 0.0.0.212, 0.0.0.213, 0.0.0.214, 0.0.0.215, 0.0.0.216, 0.0.0.217, 0.0.0.218, 0.0.0.219, 0.0.0.220, 0.0.0.221, 0.0.0.222, 0.0.0.223, 0.0.0.224, 0.0.0.225, 0.0.0.226, 0.0.0.227, 0.0.0.228, 0.0.0.229, 0.0.0.230, 0.0.0.231, 0.0.0.232, 0.0.0.233, 0.0.0.234, 0.0.0.235, 0.0.0.236, 0.0.0.237, 0.0.0.238, 0.0.0.239, 0.0.0.240, 0.0.0.241, 0.0.0.242, 0.0.0.243, 0.0.0.244, 0.0.0.245, 0.0.0.246, 0.0.0.247, 0.0.0.248, 0.0.0.249, 0.0.0.250, 0.0.0.251, 0.0.0.252, 0.0.0.253, 0.0.0.254, 0.0.0.255, 0.0.0.256, 0.0.0.257, 0.0.0.258, 0.0.0.259, 0.0.0.260, 0.0.0.261, 0.0.0.262, 0.0.0.263, 0.0.0.264, 0.0.0.265, 0.0.0.266, 0.0.0.267, 0.0.0.268, 0.0.0.269, 0.0.0.270, 0.0.0.271, 0.0.0.272, 0.0.0.273, 0.0.0.274, 0.0.0.275, 0.0.0.276, 0.0.0.277, 0.0.0.278, 0.0.0.279, 0.0.0.280, 0.0.0.281, 0.0.0.282, 0.0.0.283, 0.0.0.284, 0.0.0.285, 0.0.0.286, 0.0.0.287, 0.0.0.288, 0.0.0.289, 0.0.0.290, 0.0.0.291, 0.0.0.292, 0.0.0.293, 0.0.0.294, 0.0.0.295, 0.0.0.296, 0.0.0.297, 0.0.0.298, 0.0.0.299, 0.0.0.300, 0.0.0.301, 0.0.0.302, 0.0.0.303, 0.0.0.304, 0.0.0.305, 0.0.0.306, 0.0.0.307, 0.0.0.308, 0.0.0.309, 0.0.0.310, 0.0.0.311, 0.0.0.312, 0.0.0.313, 0.0.0.314, 0.0.0.315, 0.0.0.316, 0.0.0.317, 0.0.0.318, 0.0.0.319, 0.0.0.320, 0.0.0.321, 0.0.0.322, 0.0.0.323, 0.0.0.324, 0.0.0.325, 0.0.0.326, 0.0.0.327, 0.0.0.328, 0.0.0.329, 0.0.0.330, 0.0.0.331, 0.0.0.332, 0.0.0.333, 0.0.0.334, 0.0.0.335, 0.0.0.336, 0.0.0.337, 0.0.0.338, 0.0.0.339, 0.0.0.340, 0.0.0.341, 0.0.0.342, 0.0.0.343, 0.0.0.344, 0.0.0.345, 0.0.0.346, 0.0.0.347, 0.0.0.348, 0.0.0.349, 0.0.0.350, 0.0.0.351, 0.0.0.352, 0.0.0.353, 0.0.0.354, 0.0.0.355, 0.0.0.356, 0.0.0.357, 0.0.0.358, 0.0.0.359, 0.0.0.360, 0.0.0.361, 0.0.0.362, 0.0.0.363, 0.0.0.364, 0.0.0.365, 0.0.0.366, 0.0.0.367, 0.0.0.368, 0.0.0.369, 0.0.0.370, 0.0.0.371, 0.0.0.372, 0.0.0.373, 0.0.0.374, 0.0.0.375, 0.0.0.376, 0.0.0.377, 0.0.0.378, 0.0.0.379, 0.0.0.380, 0.0.0.381, 0.0.0.382, 0.0.0.383, 0.0.0.384, 0.0.0.385, 0.0.0.386, 0.0.0.387, 0.0.0.388, 0.0.0.389, 0.0.0.390, 0.0.0.391, 0.0.0.392, 0.0.0.393, 0.0.0.394, 0.0.0.395, 0.0.0.396, 0.0.0.397, 0.0.0.398, 0.0.0.399, 0.0.0.400, 0.0.0.401, 0.0.0.402, 0.0.0.403, 0.0.0.404, 0.0.0.405, 0.0.0.406, 0.0.0.407, 0.0.0.408, 0.0.0.409, 0.0.0.410, 0.0.0.411, 0.0.0.412, 0.0.0.413, 0.0.0.414, 0.0.0.415, 0.0.0.416, 0.0.0.417, 0.0.0.418, 0.0.0.419, 0.0.0.420, 0.0.0.421, 0.0.0.422, 0.0.0.423, 0.0.0.424, 0.0.0.425, 0.0.0.426, 0.0.0.427, 0.0.0.428, 0.0.0.429, 0.0.0.430, 0.0.0.431, 0.0.0.432, 0.0.0.433, 0.0.0.434, 0.0.0.435, 0.0.0.436, 0.0.0.437, 0.0.0.438, 0.0.0.439, 0.0.0.440, 0.0.0.441, 0.0.0.442, 0.0.0.443, 0.0.0.444, 0.0.0.445, 0.0.0.446, 0.0.0.447, 0.0.0.448, 0.0.0.449, 0.0.0.450, 0.0.0.451, 0.0.0.452, 0.0.0.453, 0.0.0.454, 0.0.0.455, 0.0.0.456, 0.0.0.457, 0.0.0.458, 0.0.0.459, 0.0.0.460, 0.0.0.461, 0.0.0.462, 0.0.0.463, 0.0.0.464, 0.0.0.465, 0.0.0.466, 0.0.0.467, 0.0.0.468, 0.0.0.469, 0.0.0.470, 0.0.0.471, 0.0.0.472, 0.0.0.473, 0.0.0.474, 0.0.0.475, 0.0.0.476, 0.0.0.477, 0.0.0.478, 0.0.0.479, 0.0.0.480, 0.0.0.481, 0.0.0.482, 0.0.0.483, 0.0.0.484, 0.0.0.485, 0.0.0.486, 0.0.0.487, 0.0.0.488, 0.0.0.489, 0.0.0.490, 0.0.0.491, 0.0.0.492, 0.0.0.493, 0.0.0.494, 0.0.0.495, 0.0.0.496, 0.0.0.497, 0.0.0.498, 0.0.0.499, 0.0.0.500, 0.0.0.501, 0.0.0.502, 0.0.0.503, 0.0.0.504, 0.0.0.505, 0.0.0.506, 0.0.0.507, 0.0.0.508, 0.0.0.509, 0.0.0.510, 0.0.0.511, 0.0.0.512, 0.0.0.513, 0.0.0.514, 0.0.0.515, 0.0.0.516, 0.0.0.517, 0.0.0.518, 0.0.0.519, 0.0.0.520, 0.0.0.521, 0.0.0.522, 0.0.0.523, 0.0.0.524, 0.0.0.525, 0.0.0.526, 0.0.0.527, 0.0.0.528, 0.0.0.529, 0.0.0.530, 0.0.0.531, 0.0.0.532, 0.0.0.533, 0.0.0.534, 0.0.0.535, 0.0.0.536, 0.0.0.537, 0.0.0.538, 0.0.0.539, 0.0.0.540, 0.0.0.541, 0.0.0.542, 0.0.0.543, 0.0.0.544, 0.0.0.545, 0.0.0.546, 0.0.0.547, 0.0.0.548, 0.0.0.549, 0.0.0.550, 0.0.0.551, 0.0.0.552, 0.0.0.553, 0.0.0.554, 0.0.0.555, 0.0.0.556, 0.0.0.557, 0.0.0.558, 0.0.0.559, 0.0.0.560, 0.0.0.561, 0.0.0.562, 0.0.0.563, 0.0.0.564, 0.0.0.565, 0.0.0.566, 0.0.0.567, 0.0.0.568, 0.0.0.569, 0.0.0.570, 0.0.0.571, 0.0.0.572, 0.0.0.573, 0.0.0.574, 0.0.0.575, 0.0.0.576, 0.0.0.577, 0.0.0.578, 0.0.0.579, 0.0.0.580, 0.0.0.581, 0.0.0.582, 0.0.0.583, 0.0.0.584, 0.0.0.585, 0.0.0.586, 0.0.0.587, 0.0.0.588, 0.0.0.589, 0.0.0.590, 0.0.0.591, 0.0.0.592, 0.0.0.593, 0.0.0.594, 0.0.0.595, 0.0.0.596, 0.0.0.597, 0.0.0.598, 0.0.0.599, 0.0.0.600, 0.0.0.601, 0.0.0.602, 0.0.0.603, 0.0.0.604, 0.0.0.605, 0.0.0.606, 0.0.0.607, 0.0.0.608, 0.0.0.609, 0.0.0.610, 0.0.0.611, 0.0.0.612, 0.0.0.613, 0.0.0.614, 0.0.0.615, 0.0.0.616, 0.0.0.617, 0.0.0.618, 0.0.0.619, 0.0.0.620, 0.0.0.621, 0.0.0.622, 0.0.0.623, 0.0.0.624, 0.0.0.625, 0.0.0.626, 0.0.0.627, 0.0.0.628, 0.0.0.629, 0.0.0.630, 0.0.0.631, 0.0.0.632, 0.0.0.633, 0.0.0.634, 0.0.0.635, 0.0.0.636, 0.0.0.637, 0.0.0.638, 0.0.0.639, 0.0.0.640, 0.0.0.641, 0.0.0.642, 0.0.0.643, 0.0.0.644, 0.0.0.645, 0.0.0.646, 0.0.0.647, 0.0.0.648, 0.0.0.649, 0.0.0.650, 0.0.0.651, 0.0.0.652, 0.0.0.653, 0.0.0.654, 0.0.0.655, 0.0.0.656, 0.0.0.657, 0.0.0.658, 0.0.0.659, 0.0.0.660, 0.0.0.661, 0.0.0.662, 0.0.0.663, 0.0.0.664, 0.0.0.665, 0.0.0.666, 0.0.0.667, 0.0.0.668, 0.0.0.669, 0.0.0.670, 0.0.0.671, 0.0.0.672, 0.0.0.673, 0.0.0.674, 0.0.0.675, 0.0.0.676, 0.0.0.677, 0.0.0.678, 0.0.0.679, 0.0.0.680, 0.0.0.681, 0.0.0.682, 0.0.0.683, 0.0.0.684, 0.0.0.685, 0.0.0.686, 0.0.0.687, 0.0.0.688, 0.0.0.689, 0.0.0.690, 0.0.0.691, 0.0.0.692, 0.0.0.693, 0.0.0.694, 0.0.0.695, 0.0.0.696, 0.0.0.697, 0.0.0.698, 0.0.0.699, 0.0.0.700, 0.0.0.701, 0.0.0.702, 0.0.0.703, 0.0.0.704, 0.0.0.705, 0.0.0.706, 0.0.0.707, 0.0.0.708, 0.0.0.709, 0.0.0.710, 0.0.0.711, 0.0.0.712, 0.0.0.713, 0.0.0.714, 0.0.0.715, 0.0.0.716, 0.0.0.717, 0.0.0.718, 0.0.0.719, 0.0.0.720, 0.0.0.721, 0.0.0.722, 0.0.0.723, 0.0.0.724, 0.0.0.725, 0.0.0.726, 0.0.0.727, 0.0.0.728, 0.0.0.729, 0.0.0.730, 0.0.0.731, 0.0.0.732, 0.0.0.733, 0.0.0.734, 0.0.0.735, 0.0.0.736, 0.0.0.737, 0.0.0.738, 0.0.0.739, 0.0.0.740, 0.0.0.741, 0.0.0.742, 0.0.0.743, 0.0.0.744, 0.0.0.745, 0.0.0.746, 0.0.0.747, 0.0.0.748, 0.0.0.749, 0.0.0.750, 0.0.0.751, 0.0.0.752, 0.0.0.753, 0.0.0.754, 0.0.0.755, 0.0.0.756, 0.0.0.757, 0.0.0.758, 0.0.0.759, 0.0.0.760, 0.0.0.761, 0.0.0.762, 0.0.0.763, 0.0.0.764, 0.0.0.765, 0.0.0.766, 0.0.0.767, 0.0.0.768, 0.0.0.769, 0.0.0.770, 0.0.0.771, 0.0.0.772, 0.0.0.773, 0.0.0.774, 0.0.0.775, 0.0.0.776, 0.0.0.777, 0.0.0.778, 0.0.0.779, 0.0.0.780, 0.0.0.781, 0.0.0.782, 0.0.0.783, 0.0.0.784, 0.0.0.785, 0.0.0.786, 0.0.0.787, 0.0.0.788, 0.0.0.789, 0.0.0.790, 0.0.0.791, 0.0.0.792, 0.0.0.793, 0.0.0.794, 0.0.0.795, 0.0.0.796, 0.0.0.797, 0.0.0.798, 0.0.0.799, 0.0.0.800, 0.0.0.801, 0.0.0.802, 0.0.0.803, 0.0.0.804, 0.0.0.805, 0.0.0.806, 0.0.0.807, 0.0.0.808, 0.0.0.809, 0.0.0.810, 0.0.0.811, 0.0.0.812, 0.0.0.813, 0.0.0.814, 0.0.0.815, 0.0.0.816, 0.0.0.817, 0.0.0.818, 0.0.0.819, 0.0.0.820, 0.0.0.821, 0.0.0.822, 0.0.0.823, 0.0.0.824, 0.0.0.825, 0.0.0.826, 0.0.0.827, 0.0.0.828, 0.0.0.829, 0.0.0.830, 0.0.0.831, 0.0.0.832, 0.0.0.833, 0.0.0.834, 0.0.0.835, 0.0.0.836, 0.0.0.837, 0.0.0.838, 0.0.0.839, 0.0.0.840, 0.0.0.841, 0.0.0.842, 0.0.0.843, 0.0.0.844, 0.0.0.845, 0.0.0.846, 0.0.0.847, 0.0.0.848, 0.0.0.849, 0.0.0.850, 0.0.0.851, 0.0.0.852, 0.0.0.853, 0.0.0.854, 0.0.0.855, 0.0.0.856, 0.0.0.857, 0.0.0.858, 0.0.0.859, 0.0.0.860, 0.0.0.861, 0.0.0.862, 0.0.0.863, 0.0.0.864, 0.0.0.865, 0.0.0.866, 0.0.0.867, 0.0.0.868, 0.0.0.869, 0.0.0.870, 0.0.0.871, 0.0.0.872, 0.0.0.873, 0.0.0.87

## 4. Tuya devices: pet feeder, lamp

Tuya is a global IoT platform that provides smart device solutions, enabling easy integration and control of various smart products. In this project, we use Tuya-controlled pet feeder and lamp, which can be managed through the Home Assistant platform. Finally, two tuya devices were added: pet feeder and LDV\_Lamp, which we can switch on/off using “controls” and check any state changes in “logbook” (Figure 4.1).

↑ Device	Manufacturer	Model	Area	Integration
 LDV_LAMP	Tuya	Tuya generic (bf30b7fb4...)	—	LocalTuya
 Pet feeder	Tuya	Tuya generic (bfd67fe2ce...)	—	LocalTuya

Figure 4.1 - Tuya devices: Pet Feeder and lamp

**Pet Feeder:** The smart pet feeder allows for scheduled feeding times and portion control, ensuring that pets are fed on time, even when the owner is not home. It can be controlled remotely through Home Assistant, providing convenience and peace of mind. Number of portions can be changed by using the control button (Figure 4.2).




Figure 4.2 - Pet Feeder control

### Adding a Tuya Pet Feeder to Home Assistant (made by Taycan):

[https://student-wiki.eolab.de/doku.php?id=amc:ss2024:bird\\_feeder:ha\\_installation](https://student-wiki.eolab.de/doku.php?id=amc:ss2024:bird_feeder:ha_installation)

**Lamp:** The Tuya smart lamp offers remote control and automation capabilities, allowing users to adjust lighting conditions based on time of day, occupancy, or other triggers. It enhances home comfort and energy efficiency. Controll button allows to turn on/off the lamp (Figure 4.3).




Figure 4.3 - Lamp control

## Adding a Tuya Lamp to Home Assistant

To add a Tuya lamp to Home Assistant, start by setting up a Tuya account and app. Download the Tuya Smart or Smart Life app from the App Store or Google Play, and create an account or log in if you already have one. Add the lamp to the app by putting it in pairing mode ( by turning it on and off a few times or holding a button) and following the in-app instructions.

Next, configure Home Assistant by accessing it via a web browser. Navigate to the Integrations section under Configuration and click the “+ Add Integration” button. Search for and select Tuya from the list. Enter your Tuya app credentials (email and password), select the appropriate Tuya region, and input the API key and secret from the Tuya IoT Platform.

The most **challenging point** in the configuration of devices is to find a local key, usually most necessary data is filled in automatically. To find the local key follow through these steps: developer tuya platform/cloud/Api explorer/device management/ query devices in project.

Home Assistant will then connect to your Tuya account and sync your devices. Ensure the Tuya lamp appears in Home Assistant by checking the Entities section under Configuration.

---

## **5. Zigbee devices: motion and temperature sensors.**

This setup integrates a Zigbee motion sensor (Figure 5.1) and a temperature/humidity sensor (Figure 5.2) for smart home automation. The motion sensor is used to create scenes, such as activating a pet feeder, while the temperature/humidity sensor helps practice data collection with InfluxDB and Home Assistant (HA).



Figure 5.1 - Motion sensor



Figure 5.2 - Temperature/humidity sensor

Two devices are listed: \_TZ1800\_fcdjzz3s TY0202, located in the living room, with 96% battery, and \_TZ3000\_xr3htd96 TS0201, with 100% battery (Figure 5.3). Both are integrated with Zigbee Home Automation.

Device	Manufacturer	Model	Area	Integration	Battery
_TZ1800_fcdjzz3s TY0202	_TZ1800_fcdjzz3s	TY0202	Гостиная	Zigbee Home Automation	96%
_TZ3000_xr3htd96 TS0201	_TZ3000_xr3htd96	TS0201	-	Zigbee Home Automation	100%

Figure 5.3 - Zigbee devices

The dashboard displays sensor data, including motion detection (Figure 5.4), humidity at 61.6%, and temperature at 23.9°C (Figure 5.5). Configuration settings and firmware updates are available, and the logbook records motion events and button presses.

Sensors		Logbook	
	Motion		July 2, 2024
			_TZ1800_fcdjzz3s TY0202 Motion cleared (no motion detected) 1:51:25 PM - 1 hour ago
ADD TO DASHBOARD			
Configuration			Up-to-date
	Firmware		_TZ1800_fcdjzz3s TY0202 Motion detected motion 1:50:17 PM - 1 hour ago
			_TZ1800_fcdjzz3s TY0202 Motion cleared (no motion detected) 1:49:18 PM - 1 hour ago

Figure 5.4 - Motion sensor state

Sensors		Logbook	
	Humidity	61.6%	July 2, 2024
	Temperature	23.9 °C	_TZ3000_xr3htd96 TS0201 Identify changed to July 2, 2024 at 1:05 PM triggered by service Button: Press 1:05:54 PM - 2 hours ago - ha_project
ADD TO DASHBOARD			
			TZ3000_xr3htd96 TS0201 Firmware turned

Figure 5.5 - Temperature and humidity data

## 6. Node-red: main nodes. Automatisation: pet feeder and motion sensor. E-mail Node Configuration.

Node-RED is a powerful, flow-based development tool for visual programming. Node-RED uses a visual editor to create “flows” by connecting nodes.

Node-RED excels in home automation by enabling complex workflows:

- Device Control: Manage lights, sensors, and appliances.
- Data Processing: Collect and visualize sensor data.
- Automation Logic: Implement rules for automated actions, like scheduling a pet feeder.
- Notifications and Alerts: Set up alerts via email or SMS.
- Third-Party Integration: Connect with external services like weather APIs and voice assistants.

### Pet feeder and motion sensor configuration

Task: to trigger the pet feeder when motion is detected. Firstly, node-red was installed.

This Node-RED flow diagram shows a simple setup for a pet feeder system using a state node, a debug node, and a call service node (Figure 6.1).






Figure 6.1 - Pet feeder and motion sensor flow

1. MotionSensor (state node): This node represents a motion sensor that detects movement. It is currently off (as indicated by the red circle and the text “off at: Jul 2, 13:51”) (Figure 6.2).



1. debug 2: This node is connected to the MotionSensor node and is likely used to output debug information to the debug pane in Node-RED. It helps in monitoring the data being passed from the motion sensor.
2. feed (call service node): This node is connected to the MotionSensor node as well and represents the pet feeder mechanism. When the motion sensor detects movement, it triggers this node to activate the feeder (Figure 6.3).



The flow works as follows:

- When the MotionSensor detects motion, it sends a signal to both the debug node and the feed node.
- The debug node logs this event for monitoring and troubleshooting.
- The feed node activates the pet feeder mechanism to dispense food.

Test video with cat: <https://youtube.com/shorts/Tk14my7ZAQo?feature=share>

## Lamp and motion sensor

The next Node-RED flow diagram (Figure 6.4) is designed to control a light based on motion detection and inactivity. The components are as follows:

- MotionSensor (state node): This node detects motion and is currently off (indicated by the red

circle and “off at: Jul 2, 13:51”).

- debug 1: This node is used for debugging purposes, outputting messages to the debug pane.
- Light (call service node): This node represents a light that will be turned on when motion is detected.
- NoMotion5min: This node detects if there has been no motion for 5 minutes.
- TurnOffLightDuelInactivity (call service node): This node turns off the light if no motion is detected for a certain period.
- delay 5s: This node introduces a 5-second delay before processing further actions.




Figure 6.4 - Lamp and motion sensor

Test video with cat:

- light on: <https://youtube.com/shorts/wmEXFubPh1w?feature=share>
- light off: <https://youtube.com/shorts/wmEXFubPh1w?feature=share>

## Email Node Configuration

This Node-RED flow is set up to send an email notification when the state of a device changes (e.g., a lamp or pet feeder) (Figure 6.5).




Figure 6.5 - Email Node Configuration flow

1. State Change Node: add a state\_changed node to detect changes in a device (e.g., a lamp).
1. Email Node Configuration (Figure 6.6):
  - Add and configure an email node to send notifications.
  - Set the recipient, SMTP server (smtp.gmail.com), port (465 for SSL or 587 for TLS), and sender's credentials (Figure 6.7).

Edit email node

Delete Cancel Done

**Properties**

**Name**: lamp activated

**To**: vst.mail.private@gmail.com

**Server**: smtp.gmail.com

**Port**: 465  Use secure connection.

**Auth type**: Basic

**UserId**: zacepina200900@gmail.com

**Password**: .....

TLS option  Check server certificate is valid

Figure 6.6 - Email Node Configuration

**ATTENTION: if it doesn't work, check google account security settings!**




Figure 6.7 - Email is sent

Test video with cat: <https://youtube.com/shorts/93Olb3B-sbU?feature=share>

## 7. InfluxDB: database. Graphics

InfluxDB is a special type of database designed to handle and store data that changes over time, known as time-series data.

- Efficient Data Storage: Stores large amounts of sensor data efficiently.
- Fast Data Handling: Quickly processes and stores data from many sensors at once.
- Powerful Analysis: Easily analyze and query data to find trends and patterns.

- Great Visualization: Create real-time and historical dashboards with tools like Grafana.
- Scalable: Handles increasing amounts of data as your smart home grows.
- Automatic Data Management: Automatically manages old data to save space.
- Customizable: Tailor storage and queries to fit your specific needs.
- Strong Community Support: Lots of resources and plugins available.
- Open Source: Free to use and modify as needed.

### Steps to Connect InfluxDB to Home Assistant

- Install the InfluxDB Add-on
- Start the Add-on
- Access the InfluxDB Web UI (Figure 7.1)



Figure 7.1 - InfluxDB: open WEB UI

- Configure Home Assistant to Use InfluxDB: create the database and user in InfluxDB, after open the configuration.yaml file in HA, write configuration code (according to your data) (Figure 7.2).

```

 19
 20 influxdb:
 21   host: localhost
 22   port: 8086
 23   database: smart_home
 24   username: ha_project
 25   password: project_amc
 26   max_retries: 3
 27   default_measurement: state
 28

```

Figure 7.2 - Configuration code for database InfluxDB

For example, we can observe temperature and humidity (Figure 7.3) (data from the sensor) changing through the day and plot the diagram (Figure 7.4).




Figure 7.3 - InfluxDB: choosing values




Figure 7.4 - InfluxDB: humidity diagram

## Reference

1. <https://www.raspberrypi.com/documentation/>
2. <https://www.home-assistant.io/getting-started/concepts-terminology/>
3. <https://www.home-assistant.io/integrations/zha/>

From: <https://student-wiki.eolab.de/> - **HSRW EOLab Students Wiki**

Permanent link:

[https://student-wiki.eolab.de/doku.php?id=amc:ss2024:home\\_assistant\\_server:start&rev=1722385164](https://student-wiki.eolab.de/doku.php?id=amc:ss2024:home_assistant_server:start&rev=1722385164)

Last update: **2024/07/31 02:19**

